2025/12/19 02:58 1/2 Using Slackware-current

Using Slackware-current

Note: I have removed a section on DE-less installation since my current slackware installations ARE, in fact, DE-less.

Note: I have also removed a section on hijacking other Linux system - this, here, turned out to be VERY similar to what needed to be done.

[LastUpdated20210620]

I need to use GTK3 version that is newer that the one on 14.2, so I tried the development version (**slackware64-current**). I have done the same once (pre-11), so I am aware that there can be some issues when doing this. I am happy to say that I AM writing this on a slackware64-current (15.0 beta?) installation on my laptop.

So, this is a little note to my future self (or anybody that may be find this useful **DISCLAIMER: Use this at your own risk!**). I am doing this while still using Devuan and I want to keep that for backup, in case things go wrong. (On a side note, the reason I use Devuan was because of the GTK3 version.) So, I have an extra partition that I have reformatted and prepared to download the stuffs I need.

- download official packages (getslack)
 - create download path: <mount-path>/home/share/slackware
 - create custom getslack config .getslack
 - ∘ set VERS=current
 - exclude kde & xfce
- setup EFI boot
 - bzImage in kernels/huge.s (rename to vmlinuz)
 - initrd.img in isolinux/ (this has the slackware setup)
- · boot and run installation as usual
 - DO NOT format partition (packages are there!)
 - pick packages from mounted path
 - manually set kernel to boot (i use huge generic needs initramfs)
- boot newly installed slackware
 - remove gnuchess and xaos packages
 - make sure vim does not create backups (edit usr/share/vim/vimrc)
 - allow dmesq for user
 - append etc/rc.d/rc.local ← echo 0 >
 /proc/sys/kernel/dmesg_restrict
 - just for personal reference, some useful info on using nmcli

```
nmcli r[adio] wifi
nmcli r[adio] wifi on

nmcli d[evice] wifi list
nmcli d[evice] wifi connect <ssid> password <pass> ifname <wlan0>

nmcli c[onnection] show
nmcli c[onnection] down <ssid>
nmcli c[onnection] up <ssid>
```

customize etc/xdg/user-dirs.defaults (standard default paths)

Last update: 2025/01/11 17:25

From:

http://azman.unimap.edu.my/dokuwiki/ - Azman @UniMAP

Permanent link:

http://azman.unimap.edu.my/dokuwiki/doku.php?id=linux:slack_1current&rev=1736587519

Last update: 2025/01/11 17:25

