

# FreeBSD Tweaks

Maybe useful to some...

## ZeroConf

- avahi & multicast dns

```
pkg install -y avahi-app nss_mdns
```

- enable avahi daemon in rc.conf:

```
avahi_daemon_enable="YES"
```

- modify the hosts: line in nsswitch.conf:

```
hosts: files dns mdns
```

## User Account

- by default root shell is csh and user is sh - edit .shrc to get prettier prompt

```
PS1=`whoami`@\H:\w\$ "
```

- (IF using slim) to enable x environment after slim login, create ~/.xinitrc for each user:

```
exec /usr/local/bin/mate-session
```

## Git

1. 'git log' output does not show colorized output
  - can see the escape sequence
  - so, as user, type

```
git config --global core.pager "ls -r"
```

## Network Configuration

**Note** DHCP client is dhclient - simply run `dhclient <interface>` when booting to console and using something like USB tethering.

Configure (wireless) network interface (in case was not done during installation)

- FreeBSD has network interface name - based on the driver name (e.g. sis, re)
  - to find this, use `pciconf -lv`
- for normal wired connection (e.g. re0), add to 'rc.conf'

```
ifconfig_re0="DHCP"
```

- for a wireless connection (e.g. ath0), add in

```
wlan_ath0="wlan0"
ifconfig_wlan0="DHCP"
```

- for a secured wireless connection (e.g. WPA protected), add in

```
wlan_ath0="wlan0"
ifconfig_wlan0="WPA SYNC DHCP"
```

also, append '/etc/wpa\_supplicant.conf'

```
network={
    ssid="the_ssid"
    psk="the_psk"
}
```

- not sure why but wlan0 was not auto-created?
  - from official handbook, do `ifconfig wlan0 create wlandev ath0`
  - to start up and scan, do `ifconfig wlan0 up scan`
  - or just scan, do `ifconfig wlan0 list scan`

## Graphics

Driver for ASUS E5450 Graphics Card (based on Radeon 5450?)

- install driver

```
pkg install -y xf86-video-ati
```

- to load on startup, edit rc.conf:

```
kld_list="radeonkms"
```

For Intel Graphics (Asus H81M-K Motherboard)

- install driver

```
pkg install -y xf86-video-intel
```

- to load on startup, edit rc.conf:

```
kld_list="i915kms"
```

- install something? (for kernel?)

```
pkg install -y drm-kmod
```

- some older ones require drm-fake-kmod instead

## Web Server

### Web Server (Apache)

- find apache package(s)

```
pkg search apache2 | grep -e "^apache2"
```

- install apache package(s)

```
pkg install -y php56 mod_php56 php56-mbstring php56-mcrypt php56-zlib
php56-curl php56-gd php56-json
```

- to load on startup, edit rc.conf:

```
apache24_enable="YES"
```

- default document path is /usr/local/www/apache24/data/

### Server Script (PHP)

- find php package(s)

```
pkg search php5 | grep -e "^php5"
```

- install php package(s)

```
pkg install -y apache24
```

- configure /usr/local/etc/apache24/Includes/php.conf:

```
<IfModule dir_module>
    DirectoryIndex index.php index.html
    <FilesMatch "\.php$">
        SetHandler application/x-httpd-php
    </FilesMatch>
    <FilesMatch "\.phps$">
        SetHandler application/x-httpd-php-source
    </FilesMatch>
</IfModule>
```

- copy template configuration file # cp /usr/local/etc/php.ini-production /usr/local/etc/php.ini

### Data-base (mysql/mariadb)

- install package(s)

```
pkg install mariadb103-server mariadb103-client php56-mysqli
```

- to load on startup, edit rc.conf:

```
mysql_enable="YES"
```

- by default, it listens to remote request at port 3306. to check:

```
# lsof -i4 -i6  
# sockstat -4 -6
```

- to allow local access only, edit rc.conf:

```
mysql_args="--bind-address=127.0.0.1"
```

- now, to make sure all is okay:

```
# lsof -i4 -i6 | grep mysql  
# netstat -an | grep 3306  
# sockstat -4 -6 | grep 3306
```

## Creating Disk Layout for Bootable USB

### Label for Partitions/Slices

This is nice to have in / etc/ fstab when device assignment may change (e.g. usb drive on different machine may be assigned differently)

For ufs,

```
# tunefs -L <label> /dev/da0p?
```

To check if assigned,

```
# ls /dev/ufs
```

For swap,

```
# glabel label <label> /dev/da0p?
```

To check if assigned,

```
# ls /dev/label
```

Then, / etc/ fstab entry can be like,

```
/dev/label/<label>    none    swap    sw    0    0
/dev/ufs/<label>    /    ufs    rw    1    1
```

## Disk Utility "gpart"

Show partition

```
# gpart show
```

Resize partition

```
# gpart resize -i 3 da0
```

Not really gpart stuff, but don't forget to grow FS to fit new size

```
# growfs /dev/da0p3
```

## Access to Linux ExtFS

At the moment, full R/W access for Ext2, Journal-less for Ext3 and R/O for Ext4.

```
# kldload ext2fs
# mount -t ext2fs /dev/<slice> <mount-path>
```

From:  
<http://azman.unimap.edu.my/dokuwiki/> - Azman @UniMAP



Permanent link:  
[http://azman.unimap.edu.my/dokuwiki/doku.php?id=freebsd:freebsd\\_3tweaks&rev=1739505320](http://azman.unimap.edu.my/dokuwiki/doku.php?id=freebsd:freebsd_3tweaks&rev=1739505320)

Last update: 2025/02/14 11:55